Auto-Tune

Intonation Correcting Plug-In

User's Manual



© 2000 Antares Audio Technologies. All Rights Reserved.

All trademarks are the property of their respective owners.

Antares Audio Technologies 464 Montery Ave. 2nd Floor Los Gatos, CA 95030

voice: (888) 332-2636 fax: (408) 399-0036

email: info@antarestech.com web: www.antarestech.com

Printed in USA Rev 1 04/2000

Auto-Tune software and this User's Manual are protected by copyright law. Making copies, adaptations, or derivative works without the prior written authorization of Antares Audio Technologies, is prohibited by law and constitutes a punishable violation of the law.

Antares Audio Technologies retains all ownership rights to the Auto-Tune software and other software offered by Antares Audio Technologies and their documentation. Use of Auto-Tune is limited by the license agreement printed on the envelope containing your original diskette and distributed on files with Auto-Tune. This license agreement also appears below.

All trademarks are the property of their respective holders.

Auto-Tune License Agreement

Carefully read all the terms and conditions of this license agreement. If you do not agree with the terms and conditions of this Agreement, notifying Antares Audio Technologies and destroying all copies of the manual, and erasing Auto-Tune from all machine-readable media, whether on-line or on archival copies.

Software License Agreement

Antares Audio Technologies grants you a non-transferable, non-exclusive license to use Auto-Tune, under the terms and conditions stated in this agreement. Use of Auto-Tune indicates your agreement to the following terms and conditions.

License

You may:

- 1. use Auto-Tune on only one computer at a time;
- physically transfer the program from one computer to another, provided that the program is used on only one computer at a time.

You may not:

- make copies of Auto-Tune or of the user manual in whole or in part except as expressly provided for in this agreement. Your right to copy Auto-Tune and the user manual is limited by copyright law. Making copies, verbal or media translations, adaptations, derivative works, or telecommunication data transmission of Auto-Tune without prior written authorization of Antares Audio Technologies, is prohibited by law and constitutes a punishable violation of the law.
- make alteration or modifications to Auto-Tune (or any copy) or disassemble or decompile Auto-Tune (or any copy), or attempt to discover the source code of Auto-Tune.
- 3. sub license, lease, lend, rent, or grant other rights in all or any portion of Auto-Tune (or any copy) to others.

Term of the Agreement

This agreement is effective until terminated by you or Antares Audio Technologies. You may terminate the agreement at any time by notifying Antares Audio Technologies and destroying all copies of the manual, and erasing Auto-Tune from all machine-readable media, whether on-line or on archival copies.

In the event of breach of any of the terms of this agreement, you shall pay the attorney's fees of Antares Audio Technologies that are reasonably necessary to enforce the agreement plus resulting damages.

Limited Warranty and Disclaimer

Auto-Tune AND ACCOMPANYING MATERIALS ARE PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

Antares Audio Technologies does not warrant that the functions contained in the program will meet your requirements. The entire risk as to the use, quality, and performance of Auto-Tune is with you. Antares Audio Technologies warrants the diskettes on which the program is furnished to be free from defects in materials and workmanship under normal use for a period of ninety (90) days from the day of delivery to you as evidenced by a copy of your receipt. Antares Audio Technologies' entire liability and your exclusive remedy as to the diskettes will be the replacement of the diskettes.

SOME JURISDICTIONS DO NOT ALLOW LIMITATIONS ON HOW LONG AN IMPLIED WARRANTY LASTS, SO THE ABOVE LIMITATION MAY NOT APPLY TO YOU. THIS WARRANTY GIVES YOU SPECIFIC LEGAL RIGHTS. YOU MAY ALSO HAVE OTHER RIGHTS WHICH VARY FROM JURISDICTION TO JURISDICTION.

Limitation of Liability

IN NO EVENT WILL ANTARES BE LIABLE FOR ANY DAMAGES, INCLUDING LOSS OF DATA, LOST PROFITS OR OTHER SPECIAL, INCIDENTAL, CONSEQUENTIAL OR INDIRECT DAMAGES ARISING FROM THE USE OF Auto-Tune OR ACCOMPANYING MATERIALS. THIS LIMITATION WILL APPLY EVEN IF ANTARES OR ITS AUTHORIZED AGENT HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH

DAMAGE. YOU ACKNOWLEDGE THAT THE LICENSE FEE REFLECTS THIS ALLOCATION OF RISK. SOME JURISDICTIONS DO NOT ALLOW LIMITATION OR EXCLUSION OF LIABILITY FOR INCIDENTAL OR CONSEQUENTIAL DAMAGES, SO THE ABOVE LIMITATION MAY NOT APPLY TO YOU.

Welcome!

On behalf of everyone at Antares Audio Technologies, we'd like to offer both our thanks and congratulations on your decision to purchase the Antares Auto-Tune, the most powerful intonation correction tool in the world.

Before you proceed any farther, we'd like to strongly encourage you to fill out and return the Auto-Tune registration card. To make it as easy as possible, we've included a sticker with your serial number attached to the card. The serial number also appears on the bottom of the box, but it's probably a good idea also to write it in your manual for future reference.

As an Auto-Tune owner, you are entitled to receive notification of any software upgrades, technical support, and advance announcements of upcoming products. But we can't send you stuff unless we know who and where you are. So please, send that card in.

At Antares, we are committed to excellence in quality, customer service, and technological innovation. With your purchase of the Auto-Tune, you have created a relationship with Antares which we hope will be long and gratifying. Let us know what you think. You can count on us to listen.

Again, thanks.

The Whole Antares Crew

Table of Contents

CHAPTER 1	Getting Started 7
A few words from	n Dr. Andy 7
How To Use This	s Manual 8
The Cor	ntents Of This Manual 8
	Chapter 1: Getting Started 8
	Chapter 2: Introducing Auto-Tune 8
	Chapter 3: Auto-Tune Tutorial 8
T	Chapter 4: Auto-Tune Controls 8
Installing Auto-T	
Authorizing Auto	
Proof of	Purchase: 9
Challeng	ge String: 9
Technical Support	rt 10
CHAPTER 2	Introducing Auto-Tune 11
What Is Pitch?	11
Some Terminolog	gy 12
The Purpose of P	Pitch Correction 13
How Auto-Tune	Detects Pitch 14
How Auto-Tune	Corrects Pitch 15
Auto-Tune Mode	s: Automatic and Graphical 16
The Automatic M	Iode 16
The Graphical M	ode 18

Auto-Tune Tutorial 21 **CHAPTER 3**

Lesson 1: Automatic Mode Controls 21 Lesson 2: Graphical Mode 24 Keyboard equivalents: 28 Lesson 3: A Quiz 29 Lesson 4: Precision 30 Lesson 5: Using the Make Curve Button 30

Lesson 6: Using the Make Auto Button More Information and Usage Tips 37

Auto-Tune Controls 39 **CHAPTER 4**

Automatic Mode Controls The Scale popup 39 Modern equal temperament: 39 Historical tunings: 40 Ethnic Tunings: 40 Contemporary Tunings: 41 The Key popup 42 The Edit Scale button 42 The Scale Detune slider 44 The Retune slider 45 The Tracking slider 45 The Vibrato Section 45 The Change meter 46 Graphical Mode Controls 46 The Arrow buttons 46 The Graphical tools 47 The Line tool 47 The Curve tool 47 The Pointer tool 47 The Zoom/Select tool 48 The Undo button 48 The Cut and Copy buttons 48 The Paste Button 48 The Select All Button 49 Keyboard equivalents: The Make Curve button 49 The Make Auto button 49 The Tracking slider 50 The Retune slider 51 The Playback controls 51 The Track Pitch button 51 The Correct Pitch button 52 The Buffer size control 52

CHAPTER 1 Getting Started

A few words from Dr. Andy

I remember, as if it were yesterday, sitting in my junior high school band, happily playing away on my flute, when I noticed that our conductor was screaming and jumping up and down on the podium. What was this about? Suddenly, I realized she was screaming at me. And just in time too — since I was able to duck and watch a baton fly past my head, missing me by inches. "Why [expletive] can't you play in tune?" she asked. But I was in tune. Everybody else was out of tune. It was then I began to learn about intonation.

Many artists struggle with intonation. An entire concert can be spoiled by a single sour note. Many of our most celebrated entertainers spend hours in the studio doing retake after retake, trying to sing expressively and in tune. Afterwards, their producers spend yet more time trying to correct intonation problems using inadequate tools.

Auto-Tune is dramatically changing all of that. Because of Auto-Tune, sessions can focus on feeling and expression, rather than retakes. Studio hours are reduced and production costs are lowered. Even artists in live performance situations can concentrate on interpretation, confident that any pitch inaccuracies will be caught and corrected before they make it out to the audience.

What's more, Auto-Tune is incredibly easy to use (a fact attested to by the thinness of this manual). So fire up Auto-Tune, invest a half hour or so in reading the following pages, and prepare to make intonation problems a thing of the past.

Andy Hildebrand Ph.D. Founder and Chief Scientist andy@antarestech.com

How To Use This Manual

Auto-Tune has a transparent user-interface and is extraordinarily easy to use. However, because Auto-Tune does things that have never been done before, some aspects of the user-interface will not be immediately obvious. You must read either Chapter 3, Auto-Tune Tutorial, or Chapter 4, Auto-Tune Controls, to learn the essential information you will need to operate Auto-Tune.

The Contents Of This Manual

Chapter 1: Getting Started

The chapter you are reading.

Chapter 2: Introducing Auto-Tune

This chapter explains basic facts about pitch and how Auto-Tune functions to correct for pitch errors. The basic functionality of Auto-Tune is discussed, and information you need to use it effectively is provided.

Chapter 3: Auto-Tune Tutorial

This chapter introduces you to details of how Auto-Tune works by guiding you through several tutorials. All of the important controls are explained. Also, important hints and tips are presented that will help you use Auto-Tune effectively. If you only read one chapter, read this one.

Chapter 4: Auto-Tune Controls

This chapter is reference information for all of the controls used in the Auto-Tune interface. Much of the information in this chapter is also presented in Chapter 3, however, some of the less important controls are only explained in Chapter 4.

Installing Auto-Tune

Instructions for installing Auto-Tune for your specific platform are located in the Auto-Tune Read Me file on the CD ROM. This file may also contain any last-minute Auto-Tune information that didn't make it into this manual.

Authorizing Auto-Tune

Authorization (the process by which the Auto-Tune software installed on your computer is allowed to run) is accomplished by a technique called "Challenge/Response." This is described in detail in the Read Me file, but basically, the first time you launch Auto-Tune you will be presented with a string of letters (the Challenge) and will be asked to enter another string of letters (the Response).

To receive the appropriate Response, you will need to provide us with both proof of purchase and your Challenge string. Here are the options for accomplishing this:

Proof of Purchase:

- Fill out your warranty card and fax it, with the serial number sticker attached, to (408) 399-0036. This is a preferred option in that you can be certain that it has arrived prior to your requesting your Response.
- If you have access to a scanner, scan your warranty card (after filling it
 out) with the serial number sticker attached and send it as a JPEG attachment in the same email as your Response request (see below).
- Mail us your warranty card with the serial number sticker attached. You
 should only rely on this if you don't have access to either of the other
 options, as you can never predict when it's actually going to arrive.
 (However, you should still mail the warranty card in any case, so that
 we can have it physically on file.)

Challenge String:

• Once you have reason to believe that we have received your proof of purchase, point you web browser to:

http://antarestech.com/authorize/

and simply follow the directions. You will receive your Response by return email, typically within one working day.

- If, for some reason, you do not have access to the web but do have email, copy and paste your Challenge string into an email along with your name, the product name (e.g., Auto-Tune for MAS), and your serial number and send it to: register@antarestech.com. You will receive your Response string by return email, usually within 24 hours (unless you have sent the email over a weekend, in which case you should receive it the following Monday).
- If you do not have access to the web or email, fax us your Challenge string along with your proof of purchase as described above. Be sure to include your fax number. We will fax the Response string back to you at that number.

When initially installed, Auto-Tune will run for ten days without authorization, so even if your can't contact us right away you can still use your software in the meantime. (During this period, click the "Continue" button whenever you are presented with the Authorization dialog box.) But don't procrastinate too long. After those ten days are up, you will no longer be able to launch Auto-Tune until the correct Response is entered.

Technical Support

In the unlikely event that you experience a problem using Auto-Tune, try the following:

- Make another quick scan through this manual. Who knows? You may have stumbled onto some feature that you didn't notice the first time through.
- Check our web page for tips, techniques, or any late-breaking information: www.antarestech.com
- Call your local Antares dealer.
- 4. Call us at (888) 332-2636, or (408) 399-0008 Monday through Friday between 9am and 5pm USA Pacific Standard Time.
- Email us at: techsupport@antarestech.com

For options 3, 4 and 5, please be prepared to provide the serial number of your copy of Auto-Tune.

CHAPTER 2 Introducing Auto-Tune

Auto-Tune is a breakthrough in digital signal processing (DSP) in the music industry. It puts you in control of pitch. Moreover, Auto-Tune is a precision instrument for controlling pitch, allowing you to apply nuances of intonation to any performance. These nuances were only previously available to synthesized music if the engineer involved was willing to do a lot of work.

Access to this new level of control is achieved by any Auto-Tune user who has a basic understanding of pitch and how Auto-Tune functions to correct for pitch errors. This chapter presents basic terminology and introduces Auto-Tune's operating paradigm, giving you information you need to use it effectively.


What Is Pitch?

Pitch is a quality of sound relating to the frequencies of the energy involved. Some sounds are very complex and don't involve energy of specific frequencies. Even then, there is pitch. Compare, for example the pitch of hissing steam with the rumble of an earthquake. Other sounds, although still complex, have more specific pitch. A symphony orchestra playing a scale in unison is an example of this. The waveforms involved are very complex; nonetheless, you are able to easily sense the pitch.

Vocalist and the majority of individual instruments have the most clearly defined quality of pitch. The sound-generating mechanism of these sources is a vibrating element (vocal chords, a string, an air column, etc.). The sound that is generated consists of energy at a frequency (called the fundamental) and energy at frequencies that are integer multiples of the fundamental frequency (called harmonics). These sounds have a waveform (pressure as a

Introducing Auto-Tune

function of time) that is periodic. This means that the waveform repeats itself, such as the periodic waveform shown in the diagram, below.



Other sounds are more complex. The non-periodic waveform, above, is from a violin section playing a single tone. Our ears still sense a pitch, but the waveform does not repeat itself

This non-periodic violin section is a summation of a number of individually periodic violins. The summation is non-periodic because the individual violins are slightly out of tune with respect to one another.

Some Terminology

The pitch of periodic waveforms is defined as the number of cycles per second of the waveform. This unit is named Hertz (abbreviated Hz.). The standard instrumental tuning is A3 = 440 Hz.

Pitches are often described relative to one another as intervals, or ratios of frequency. For example, two pitches are said to be one octave apart if their frequencies differ by a factor of two. Pitches which are integer multiples of one-another sound more "harmonious" when played together, whereas pitches that are not are said to be "dissonant".

Pitch ratios are measured in units called "cents". There are 1200 cents per octave. For example, two tones that are 2400 cents apart are two octaves apart and have a pitch ratio of 4 (or 1/4).

The twelve-tone Equal Tempered Scale consists of tones that are, by definition, 100 cents apart. These are called semi-tones. This scale is the ubiquitous scale used (or rather approximated) in 99.9% of all Western tonal music. The twelve equally-spaced tones of the Equal Tempered Scale happen to contain a number of intervals that approximate integer ratios in pitch. The following table shows these approximations:

Interval	Cents	Nearby Ratio	Ratio Cents
minor second	100	16/15	111.73
major second	200	9/8	203.91
minor third	300	6/5	315.64
major third	400	5/4	386.31
perfect fourth	500	4/3	498.04
tritone	600		
perfect fifth	700	3/2	701.95
minor sixth	800	8/5	813.69
major sixth	900	5/3	884.36
minor seventh	1000	16/9	996.09
major seventh	1100	15/8	1088.27
octave	1200	2	1200

TABLE 1. The Equal Tempered Scale

As you can see, the intervals in the Equal Tempered Scale are NOT equal to the harmonious integer ratios. Rather, the Equal Tempered Scale is a compromise. It became widely used because once a harpsichord or piano is tuned to that scale, any composition in any key could be played and no one chord would sound better or worse than that same chord in another key. In modern times, synthesizers can generate any intonation at any moment, allowing the use of ideal pitch ratios when ever they are desired.

The Purpose of Pitch Correction

When voices or instruments are out of tune, the emotional qualities of the performance are lost. Correcting intonation solves this problem and

restores the performance. Auto-Tune is mostly used to solve these gross intonation problems. However, as you shall see, Auto-Tune is also a precision instrument, allowing intonation to be controlled to extraordinary degrees of accuracy. This allows the tonal aspects of music to be controlled accurately and easily to achieve any desired consonance or dissonance in harmonies.

Don't try to raise the pitch more than an octave. Auto-Tune has a built-in limitation of not being able to raise a pitch more that one octave (1200 cents). This is not considered a problem since most pitch corrections will be +/-20 cents.

How Auto-Tune Detects Pitch

In order for Auto-Tune to automatically correct pitch, it must also detect the pitch of the input sound. It's easy for you to calculate the pitch of a periodic waveform: Simply measure the time between repetitions of the waveform. Divide this time into one, and you have the frequency in Hertz.

Auto-Tune does the same thing: It looks for a periodically repeating waveform and calculates the time interval between repetitions.

The pitch detection algorithm in Auto-Tune is virtually instantaneous. Like your eye-ball, it can see the repetition in a periodic sound within a few cycles. This usually occurs before the sound has sufficient amplitude to be heard. Used in combination with a slight delay (about 1 to 10 milliseconds), the output pitch can be detected and corrected without artifacts in a seamless and continuous fashion.

Auto-Tune will not detect pitch when the input waveform is not periodic. Hence, Auto-Tune will fail to tune up a violin section. (It is possible to tune up an out of tune violin section, either tuning the sound as is, or by tuning up the individual players within the sound. This is done on samples for synthesizers using the Antares Audio Technologies Infinity software. Using Infinity, you can actually made a community orchestra sound like the New York Philharmonic. But Infinity processes samples, whereas Auto-Tune is used on performances.)

Back to Auto-Tune, if the input waveform is not periodic, Auto-Tune will fail. At times, this can be a problem. Consider, for example, a breathy voice, or a voice recorded with a wind sound. The added noise is non-periodic, and Auto-Tune will have difficulty determining the pitch of this sound. There is a slider (the Tracking slider, discussed in Chapter 4) that will allow Auto-Tune to be more casual about what it calls "periodic", which will help in these cases.

If you have problems processing a particular sound, zoom it up and look at it. If it is non-periodic, Auto-Tune will not work. If you can correct that problem, by using EQ or re-recording, then those are options available to you.

The precision by which Auto-Tune detects pitch is extraordinary. At a frequency of 400 Hz and a sample rate of 44100, the Auto-Tune DSP algorithm computes the pitch to an accuracy of .0001 samples per cycle, or .0004 Hz. At this resolution, the very question "What is pitch?" becomes relevant. That is, as the pitch of typical performances continuously change, the amount of variation in pitch, even over the time of a few cycles, changes greatly in comparison to the accuracy by which Auto-Tune computes pitch. The pitch computed by Auto-Tune is a mathematical estimate of the cycle period repetition rate over the last two (or sometimes the last four) cycles.

Auto-Tune was designed to detect and correct pitches up to C6. In reality, if a pitch goes higher than C6, Auto-Tune will often interpret the pitch an octave lower. This is because it interprets a two cycle repetition as a one cycle repetition. These pitches can be corrected by the usual means. On the low end, Auto-Tune will detect pitches as low as A0 (55Hz). This range of pitches allows intonation correction to be performed on all vocals and almost all instruments.

How Auto-Tune Corrects Pitch

Auto-Tune changes the instantaneous pitch and introduces no distortion in the output. It does this using the same basic computations used in samplers to re-tuned samples.

This is different from other pitch-shifting algorithms which put noise in sounds as a result of FFT (Fast Fourier Transform) overlap-and-save algorithm phase errors. The Auto-Tune algorithm is very clean and transparent. It isn't possible to tell that a sound has been processed by Auto-Tune except that it is in-tune.

Introducing Auto-Tune

The accuracy of pitch correction in Auto-Tune is exceptional. In the worst case, a continuously varying tone can be corrected (at the discretion of the user) to within an error of at most one cycle in 80 seconds (assuming the Retune slider is set to zero). These accuracies are equivalent to the .01 cent accuracies by which the various scales of the Automatic Mode (discussed below) are internally specified. These accuracies are also equivalent to the accuracies of the clocks which control music studio functions.

Chapter three will step you through a demonstration where two badly out of tune C2's are independently tuned to the same standard with no beat cycles. (Beat cycles are the perceptual result of hearing two tones that are close in frequency. As the relative phase of the fundamental and harmonics change from in phase to out of phase, constructive and destructive reinforcement occurs which alternately makes the composite sound loud and soft.)

Auto-Tune Modes: Automatic and Graphical

Auto-Tune has two separate and distinct ways to operate, almost as if there were actually two separate programs in one package. These are called modes, and are named the Automatic Mode and the Graphical Mode. The Automatic Mode and Graphical Mode function separately; when one is active, pitch corrections of the other are not performed.

Both the Automatic and Graphical Mode allow the "bypass" button to be used. Even though bypass is a well known plug-in control, I mention it because it functions seamlessly and can be used to punch pitch correction on and off during processing.


The Automatic Mode

The Automatic Mode works by continuously tracking the pitch of the input sound and comparing it to a scale. The scale tone having pitch closest to the input is continuously identified. An output pitch is generated which is closer to the scale tone than the input pitch. You have control of the scale.

Major, minor, chromatic and 26 historical, ethnic and microtonal scales provide unprecedented control of the output tonality. Scale pitches can be disabled causing no pitch correction. Scale pitches can also be removed allowing a wider range of pitch correction for neighboring pitches. The scale can be de-tuned, allowing pitch correction to any pitch center. You also choose the key of the scale.

You have control over how rapidly, in time, the pitch adjustment to the scale tone is made. This is done with the Retune slider (fast to slow settings). Fast Retune settings are more appropriate for short duration tones and for mechanical instruments, like an oboe or clarinet. A fast setting will remove a vibrato. Slow Retune settings are appropriate for longer tones where you want expressive pitch gestures (like vibrato) to come through to the output. A slower setting can leave a vibrato unmodified but accurately adjust the pitch center to be in-tune.

The Automatic Mode can also introduce a vibrato into the sound. The Vibrato Section lets you control the depth, rate and delay of the vibrato. You can also choose the style of pitch variation in the vibrato (sine, ramp or




square). You would use the Vibrato Section when you have a vocalist who has not learned to use his (or her) own vibrato. It can also be used for special sound design effects.


A fast pitch adjustment to remove an existing vibrato can be used in conjunction with the Vibrato Section to replace a vibrato with a new one. This will not always give good results, though, (as discussed in Chapter 3), because there are usually accompanying changes in the loudness of the sound.


The Graphical Mode

The Graphical Mode is similar to the Automatic Mode in that it also continuously tracks the pitch of the incoming sound and modifies the output pitch to be closer to a desired pitch. But in the Graphical Mode, the desired pitch is not a scale tone, rather it is given graphically by you and is called the "tar-



get pitch function". As in Automatic Mode, the rate of change towards the desired pitch (the target pitch function) is controlled by the Retune slider.





In this graph, higher pitches are upwards and increasing time is to the right. The lighter (red) curve is the input sound pitch and the darker line is a target pitch function. The light, horizontal lines are scale pitches. The key annotation, scale names, scale pitches and Detune value are those defined in the Automatic Mode. They do not affect the computations of the Automatic Mode in any way. They are merely annotated on the Pitch Graph to guide you in setting the target pitch function. To change them, choose the Automatic Mode and change the Key popup, Scale popup, or the Detune slider, respectively. Moving the detune slider down (more negative) causes the horizontal line to go down (flatter).

The Graphical Mode also uses the Envelope Graph:



This graph shows the envelope of the sound whose pitch is shown in the Pitch Graph. The horizontal scale of this graph will either 1) show the entire envelope of the pitch-detected sound or 2) align the envelope to the horizontal scale and position of the Pitch Graph.

Introducing Auto-Tune

In Graphical Mode, the user draws the target pitch function using line and curve drawing tools. Complete image sizing and scrolling controls are provided. A graphical editor allows easy editing, including cut, copy and paste functions.

The basic steps you will perform in Graphical Mode are:

- Select some sound for processing. This is done in the Soundbites window.
- Bring up Auto-Tune. Set the buffer for a few seconds longer than the duration of the audio you are going to tune. Press the Track Pitch button, then play back the sound. The pitch will be detected and then displayed in the Pitch Graph as a red curve.
- Create a target pitch function using the graphical tools and adjust the Retune slider for the desired effect.
- Press Correct Pitch and play back the sound. This will cause the pitch to be corrected as specified.

In Graphical Mode, Auto-Tune sometimes identifies the pitch to be an octave lower than it really is. In these cases, simply correct the pitch as you would if the pitch was lower (ex. +/- 20 cents). Auto-Tune will apply this correction to achieve the desired result.

In Graphical Mode, it is important that the sound played back for pitch correction begins precisely at the same spot as the sound played back for pitch detection. This is because the plug-ins do not know the absolute "time-of-day". The specified target pitch will be applied to whatever sound occurs after playback begins, even if it is a completely different sound.

In other words, before you press Correct Pitch and play, make sure that the counter is set to start from the exact place you started Track Pitch.

CHAPTER 3 Auto-Tune Tutorial

"I don't want to know how it works –
I want to know how to work it!"

- Keith Emerson

This chapter introduces you to how Auto-Tune works by guiding you through several tutorials. All of the important controls are explained. Also, tips are presented that will help you use Auto-Tune effectively. If you only read one chapter, read this one.

The Auto-Tune installation process copies several audio files into the installation folder. Use these files in the exercises below.

Lesson 1: Automatic Mode Controls

This lesson will exercise the Automatic Mode controls of Auto-Tune using a synthetic sweep signal. The Automatic Mode works by continuously tracking the pitch of the input data and comparing it to a scale. The scale tone having its pitch closest to the input is identified. An output pitch is created which is closer to the scale tone than the input.

- Setup your playback so that Auto-Tune processes the file "A2-A3-A2 sweep".
- 2. Set the Key popup to A.
- Set the Retune slider to zero.
- 4. Set Bypass 'on' and play the sweep to hear the input sound.
- 5. Set Bypass 'off'. Play the sound again.


What you just heard was an A major scale. This is because Auto-Tune continuously compared the input pitch to the A major scale and corrected the output pitch so that the output was closer in pitch to the scale tones. Now do the following:

1. Press the Edit Scale button.

The left most column is labelled "do not track". Clicking in this column places a "chk" indicator. This has the effect that when the pitch of the incoming sound is close to a tone so edited, the output pitch is not changed from the input. This is like a pitch dependent bypass.

The next column is labeled "remove". Clicking in this column causes the tone to be removed from the scale, as if it were never there to begin with.

2. Press the mouse when the cursor is under the "remove" column so that the "chk" symbol appears next to the tones B, D, F# and G#. The dialog will appear



3. Press Done and play the sound again.

You just heard a A-major triad because you had removed all other tones from the scale.

On scales with more than 7 tones, the Edit Scale dialog appears with additional buttons. The "set major scale" and "set minor scale" buttons cause all tones to be removed except those nearest the diatonic Equal Tempered Scale of the current key. On microtone scales, additional "Microtonal tuning data" appears in the window that shows the cents values for various ideal intervals. These can be used to help tune up the scale by allowing you to select tones that are in tune with other pitches in the harmonic structure.

- 1. Press the Edit Scale button.
- Press the mouse under the "do not track" column so that the "chk" symbol appears across from E.
- 3. Press Done and play the sound again.

You just heard the effect of not tracking the E. Over the duration when the output should be E, Auto-Tune entered a bypass mode.

- 1. Move the Retune slider to about 30.
- 2. Play the sound again. Compare the 30 setting to the 0 setting.

The setting of 0 is fast: Auto-Tune makes instantaneous pitch changes. The setting of 30 is slower. Auto-Tune makes gradual pitch changes. This slider controls how rapidly the pitch correction is applied to the incoming pitch. The units are milliseconds. A value of zero will cause instantaneous changes from one tone to another and will completely suppress a vibrato (note that related volume changes will remain). Retune values from 10 to 50 are typical for vocals.

- 1. Set the Retune slider to 0.
- 2. Press the Edit Scale button.
- 3. Press the mouse under the "remove" column so that the "chk" symbol appears next to all the tones except F#.

Edits made using the Edit Scale dialog depend on the scale. That is, each scale retains its own edits separate from the other scales.

4. Press Done and play the sound again. As the sound is playing, slide the Scale Detune slider.

You are hearing the output pitch change with the Detune slider movement. This is because the Detune slider changes the pitch standard of the scale. If you have a tone you know that you want to use as the pitch standard, select that tone and play it in a loop. Adjust Scale Detune until the Change meter reads zero.


- 1. Set the Vibrato popup to "sine wave" and play back the sound.
- 2. Experiment with the vibrato controls to learn their effects.

∟esson 2: Graphical Mode

This lesson will show you how to use the Graphical Mode controls of Auto-Tune. The Automatic Mode and Graphical Mode function separately; when one is active, corrections of the other are not performed.

The Graphical Mode is similar to the Automatic Mode in that it continuously tracks the pitch of the incoming sound and modifies the output pitch to be closer to a desired pitch. In the Graphical Mode, the desired pitch is not a scale tone, rather it is given graphically by you and is called the "target pitch function". As in Automatic Mode, the rate of change towards the desired pitch (the target pitch function) is controlled by the Retune slider.

The Graphical Mode uses the Pitch Graph:



The appearance of the Pitch Graph is affected by the Key, Scale and Detune setting in the Automatic Mode. These parameters do not affect the computations performed in Graphical Mode. They merely provide you with information about the location of scale tones so that you may draw in your desired pitches.

The basic steps you will perform in Graphical Mode are:

- Select some sound for processing. This is done in the Soundbites window.
- Bring up Auto-Tune. Set the buffer for a few seconds longer than the duration of the audio you are going to tune. Press the Track Pitch button, then play back the sound. The pitch will be detected and then displayed in the Pitch Graph as a red curve.
- Create a target pitch function using the Graphical tools and adjust the Retune slider for the desired effect.
- Press Correct Pitch and play back the sound. This will cause the pitch to be corrected as specified.

Let's begin the tutorial:

- Setup your playback so that Auto-Tune processes the file "A2-A3-A2 sweep".
- 2. Set the Key popup to A.
- 3. Press the Graphical Mode button.
- 4. Press the Track Pitch button.
- 5. Play the sweep signal through Auto-Tune.


After the playback stops, or is stopped by you, you will have to press the "Track Pitch" button again to stop the tracking function.

In Graphical Mode, it is important that the sound played back for pitch correction begins precisely at the same spot as the sound played back for pitch detection. This is because the plug-ins do not know the absolute "time-of-day". The specified target pitch function will be applied to whatever sound occurs after playback begins, even if it is a completely different sound.

In other words, before you press Correct Pitch and play, make sure that the counter is set to start from the exact place you started Track Pitch.



1. Press the Zoom/Select tool and drag out a box on the Pitch Graph that encloses the red curve. You will see the following:






2. Press the Line tool and enter a line similar to that below. By clicking multiple points on the Pitch Graph, line segments joining the points will be drawn. If you move the cursor outside the Pitch Graph during point entry, the graph will be automatically scrolled.

To exit, double-click a point or press <esc> on the keyboard.


To erase the last point entered, press <delete> on the keyboard.



3. Press Correct Pitch and play back

20

4. Select the Curve tool, then click and hold down the mouse on the Pitch Graph. A curve will be drawn as the mouse is dragged. To exit, lift up on the mouse. Create a curve similar to the one shown:



- 5. Press Correct Pitch and play back the sound to hear the effect.
- 6. Listen to the effect of the Retune slider as you change the values between 0 and about 50.
- 7. Experiment with the Pointer tool. This tool is used to select and drag lines and curves.

Clicking on white space in the Pitch Graph causes all objects to become de-selected. Clicking on white space and dragging causes object end points to become selected. Shift-clicking (and dragging) is used to select contiguous points. Dragging off the Pitch Graph automatically scrolls the graph.

Every line or curve has two end points. If both end points are selected, the object is said to be selected. If you click on an object which is not selected, it becomes selected. If you click on an object that is already selected, it (and anything else that is selected) stays selected so you can drag it.

Dragging causes the selected objects to be moved. Any objects that have one end-point selected will be stretched during dragging. Dragging is constrained by neighboring unselected objects.

If you hold down the option key and then click to drag, the cursor will be restricted to vertical only movements. This is particularly handy after using the "Make Curve" button, discussed below.





1. Select one or more objects and play with undo, cut, copy, paste and select all.

The Auto-Tune clipboard is not shared with other Auto-Tune's. It is also not shared by other plug-ins, or other applications.

Keyboard equivalents:

The following are keyboard equivalents to the respective Graphical Mode buttons on certain platforms. Try them out and see if they work for you:


Command (Apple) Key	Function
a	Select All
z	Undo
х	Cut
С	Сору
v	Paste

TABLE 2. Edit Control Keys

Lesson 3: A Quiz

So, you think you're getting the hang of this? Well, if you really are, you'll be able to answer the question at the end of this lesson.

1. Use the techniques above to achieve the following Pitch Graph. Note the horizontal target pitch function:



2. Set the Retune slider to 0, press Correct Pitch and play back the sound to hear the effect..

The pitch you will hear is a steady tone, as you would expect.

3. Now set the Retune slider to <u>about</u> 50, press Correct Pitch and play back the sound to hear the effect...

The pitch you now hear starts out sharper and then becomes flatter. Why?

The Auto-Tune settings, including all the scale edit data, the input sound pitch, input sound envelope and target pitch data are saved with the project settings.

Lesson 4: Precision

This lesson is actually more like a demonstration to show the extraordinary precision by which Auto-Tune can track and correct intonation problems. It will, though, give you a little more practice using Auto-Tune. If this doesn't sound interesting, please proceed to Lesson 5, below, which is an important tutorial of some Graphical Mode techniques.

- Setup your playback so that Auto-Tune processes the files "C2 Ahhh v3" and "C2 Ohhh v1".
- In each Auto-Tune, set the Retune slider to 0.
- In each Auto-Tune, set the Key popup to B-flat.
- 4. In each Auto-Tune, press the Bypass buttons to bypass processing.
- Play back the sound to hear the effect.

Believe it or not, these are vocal samples from a CD of samples. Sounds nasty, doesn't it?

6. Press Bypass in each Auto-Tune so processing is occurring.

If you've done everything right, you will hear the samples so well in tune that they sound like one voice.


Lesson 5: Using the Make Curve Button

The make curve button is an important tool in Auto-Tune. It allows you to make precise and natural pitch corrections in Graphical Mode.

- Setup your playback so that Auto-Tune processes the file "Crowd All".
- Press the Graphical Mode button.
- Press the Track Pitch button.
- 4. Play the "Crowd All" file.




5. Press the Zoom/Select tool and drag out a box on the pitch view that encloses the red curve for the "-gether" part of the last word, "to-gether". You will see the following:





6. Use the zoom/select tool and drag out a selection of "-gether" in the Envelope Graph. You will see the following:



make curve


7. Press the Make Curve button. Auto-Tune will compute a new curve object from the existing pitch data.

The new curve may be difficult to see at first because it will exactly overlay the red curve.




8. Both ends of the new curve will be selected. Use the pointer tool and click on the white space of the Pitch Graph. That will cause no points to be selected.

- 9. Use the Pointer tool again and click precisely on the left end of the curve. Drag this straight up, stretching the curve so it falls along the D3 tone.
- 10. Grab the curve by clicking on it and drag it straight down so it falls on the C3 line. The Pitch Graph should now appear:



11. Set the Retune slider to 0, press Correct Pitch and play back the sound.

I can't say much for her voice in this segment, but at least this one note is a little better in tune. An alternative approach is given next:



1. Use the line tool to draw a horizontal tine as shown below.

2. Set the Retune slider to 20, press Correct Pitch and play back the sound.

Vibratos and other pitch gestures occur with related loudness gestures. Specifically, with vibratos, some vocalists produce mostly pitch variations and little loudness variations while others produce small pitch variations and a lot of loudness variations. (Some have called the latter a Tremolo.) Nonetheless, almost all voices seem to produce a combination of both pitch and related loudness variations. Therefore, trying to take an existing vibrato and change it (say speed it up) sometimes sounds unnatural because the new pitch variation does not correspond to the old loudness variation.

These considerations are also important when correcting pitch. It isn't always best to draw in a different pitch gesture at the desired pitch even though that gesture may have worked well elsewhere.

The following techniques usually work well in this regard:

The first technique uses the Make Curve button to create a curve of the
existing pitch and drag that curve up or down, or stretch it by dragging
one end vertically. The Retune slider can then be set very fast (0 to 5).
This will force a precise re-tuning, but it will sound very natural since
the target pitch curve will follow the original loudness gestures of the
voice.

The second technique is to draw a flat line segment across the duration of a tone at the desired pitch and then use the Retune slider set in the range 20 to 40. This has the effect of gently moving the pitch downwards the desired pitch. The slower values of 20 to 40 will let through a vibrato but still draw the overall pitch closer to being in tune. The average pitch will eventually settle to the given line and the pitch gestures will occur both sharper and flatter than that line. The settling time is about twice the Retune slider time. 20 to 40 will let through about one-half of a typical vibrato. Slower settings will let through more vibrato but will cause the new pitch to be reached more slowly.


Lesson 6: Using the Make Auto Button

The make auto button allows you to create pitch corrections that occur in the Automatic Mode.

- 1. Select "Crowd All".
- 2. In the Mixing board Window, assign Auto-Tune as a new insert to the desired track.
- Press the Graphical Mode button.
- 4. Press the Track Pitch button.
- 5. Play the "Crowd All" file.




6. Press the Zoom/Select tool and drag out a box on the pitch view that encloses the red curve for the "crowd all rushed" words. You will see the following:






7. Use the zoom/select tool and drag out a selection in the Envelope Graph, as shown:




make auto


8. Press the Make Auto button. Auto-Tune will compute a new curve object from the existing pitch data:



Assuming this entire phrase is at the pitch E3, then there are several problem spots, indicated above, where the pitch is being incorrectly adjusted towards neighboring tones.

- 9. To hear the processed sound that would produced in Automatic Mode. set the Graphical Mode Retune Slider to 0, (fast), press Correct Pitch and play back the sound..
- 10. Switch to the Automatic Mode and press the Edit Scale button. Press the mouse when the cursor is under the "remove" column so that the "chk" symbol appears next to the tones C, D and F.






Note how the pitch deviations from Step 9 have been removed. Also, note the "raised pitch" indicated above. This occurs because the Automatic Mode Retune slider value of 20 is slow compared to the rapidly increasing pitch that is occurring at that point in time. Even with the raised pitch, the average output pitch is centered on E3.



make auto



More Information and Usage Tips

The decision to use the Graphical Mode instead of the Automatic Mode is taken when the Automatic Mode doesn't achieve the desired result. This is most often the case when pitch errors cross the boundary from one tone to another and you don't want to mess with continually adding and removing tones from the scale.

In Graphical Mode, correcting pitch involves listening to a short passage and making several attempts at a correction. The time-of-day limitation forces you to always start playback at the same point. Hence, Auto-Tune is best used like an editor: Fix a spot, bounce it to another track with processing applied, and move on.

The Auto-Tune settings, including all the scale edit data, the input sound pitch, input sound envelope and target pitch data are saved with the project settings.

Finally, expect some strange results. I have one example where the singer relaxes at the end of a phrase. The pitch drops a minor third, which is easily corrected by a short, flat line segment and a small Retune value. But, in addition to the pitch dropping, the tone quality of the voice also softens. Getting the pitch right still leaves this strange sound...

Auto-7	[11110	Tute	wial
AUIO-I	INNP	11111	mu


CHAPTER 4 Auto-Tune Controls

"Just the facts, Ma'am"

- Bill Gannon, Dragnet

This chapter is reference text for all of the controls used in the Auto-Tune interface. This chapter simply describes the function of each control. How these controls are used together for intonation correction is described in Chapter 3, Auto-Tune Tutorial. Much of the information in this chapter is also presented in Chapter 3. However, some of the less important controls are only explained here.

Automatic Mode Controls



The Scale popup

The Scale popup selects the scale that is used. The first three scales are equal tempered. These are the ubiquitous scales currently found in Western tonal music. The other scales are historical, ethnic, and microtonal scales. An indepth discussion of these scales and their history is beyond the scope of this manual. The interested reader will find more information in "Tuning In-Microtonality In Electronic Music" by Scott R. Wilkinson, published by Hal Leonard Books. The following is a brief synopsis of the scales:

Modern equal temperament:

- major: a seven-tone equal tempered major scale.
- minor: a seven-tone equal tempered minor scale.
- Equal Tempered chrom.: a twelve-tone equal tempered chromatic scale.

Historical tunings:

- **Ling Lun**: a twelve-tone scale dating from 2700 B.C. China.
- Scholar's Lute: a seven-tone scale dating from 300 B.C. China.
- **Greek diatonic genus**: a seven-tone scale from ancient Greece.
- **Greek chromatic genus**: a seven-tone scale from ancient Greece.
- **Greek enharmonic genus**: a seven-tone scale from ancient Greece.
- Pythagorean: a twelve-tone scale dating from 600 B.C. Greece. This scale is derived by tuning twelve pure perfect fifths upward and adjusting the octaves downward. This leads to some pure intervals and some very impure intervals.
- **Just (major chromatic)**: a twelve-tone scale. Just intonation tunes the most frequently used intervals to be pure (integer ratios in frequency). These tunings depend on the mode (major or minor) and the key. This scale is tuned for major mode.
- **Just (minor chromatic)**: (See Just (major chromatic), above)
- **Meantone chrom.**: a twelve-tone scale. This tuning is a combination of Pythagorean and just tunings so that music in a wider variety of keys could be usable.
- Werckmeister III chrom.: a twelve-tone scale. This scale was a first attempt (about Bach's time) to allow an instrument to played in any scale. It was in response to this scale that Bach wrote Well-Tempered Clavier.
- Vallotti & Young chrom.: a twelve-tone scale. Another derivative of the Pythagorean scale designed to allow arbitrary keys.
- **Barnes-Bach (chromatic)**: a twelve-tone scale. A variation of the Vallotti & Young scale designed to optimize the performance of Bach's Well-Tempered Clavier.

Ethnic Tunings:

- **Indian**: This 22 tone scale is used in India to perform ragas.
- **Slendro**: This five-tone Indonesian scale is played by ensembles called gamelans.

- **Pelog**: This seven-tone Indonesian scale is more interesting than Slendro and is now the primary scale in Balinese music.
- **Arabic 1**: This 17 tone scale is the original Arabic scale adopted from the Pythagorean scale.
- **Arabic 2 (chromatic)**: This twelve-tone scale is the modern version of the Arabic scale popular in Arabic music today.

Contemporary Tunings:

Equal tempered scales with a large number of tones are typically used to play common tonal harmony with greater purity of intervals and chords. The typical approach is to analyze a passage (or less) of music and select tones from a scale that will best approximate the desired pure intervals.

- 19 Tone: This scale has greater purity of minor thirds and major thirds (and conversely, minor and major sixths) than twelve-tone equal temperament. A disadvantage is that perfect fifths and narrower than those found in twelve-tone equal temperament.
- 24 Tone: Also know as the quarter tone scale, this scale is used for variety but has no advantage in terms of ratios that better approximate pure intervals.
- 31 Tone: In addition to intervals that better approximate pure intervals, this scale also contains good approximations to Indonesian pelog and slendro scales.
- **53 Tone**: Related mathematically to the cycle of fifths, the 53-tone scale has very pure major and minor thirds, and fifths and fourths.
- Partch: Harry Partch is considered the father of modern microtonality.
 This scale was devised by him and used in instrument building and performances.
- Carlos Alpha: Wendy Carlos performed extensive computer analysis to devise a number of equal tempered scales with good approximations for the primary harmonic intervals and their inversions. This scale is good at approximating the primary intervals including 7/4. This scale divides the octave into 15.385 steps forming intervals of 78.0 cents.
- Carlos Beta: This scale divides the octave into 18.809 steps forming intervals of 63.8 cents.

Auto-Tune Controls

- Carlos Gamma: This scale achieves perfect purity of the primary intervals 3/2, 4/3 and 5/4. This scale divides the octave into 34.188 steps forming intervals of 35.1 cents.
- **Harmonic (chromatic)**: This twelve-tone scale is created in the partials in the fifth octave of the harmonic series. The scale degrees that correspond to the classic just intervals are the major second, major third, perfect fifth and major seventh.




The Key popup

This determines the pitch of the first tone of the scale according to the standard A3 = 440 Hertz. For example, if you select D, the current scale will have D3 as its root and will be tuned to D3 = 440 * 2 / 3 = 293.33 Hz which is exactly 600 cents below A3 = 440 Hz.



The Edit Scale button

Press the Edit Scale button to see the scale editing dialog. Edits made using this dialog depend on the scale. That is, each scale retains its own edits separate from the other scales. If a seven tone scale is being edited, the Edit Scale dialog appears:




The top line shows the current scale as selected from the Scale popup. The second line shows the current key.

The left most column is labelled "do not track". Clicking in this column places a "chk" indicator. This has the effect that when the pitch of the incoming sound is close to a tone so edited, the output pitch is not changed from the input. This is like a pitch dependent bypass.

The next column is labeled "remove". Clicking in this column causes the tone to be removed from the scale, as if it were never there to begin with.


The next column is the note name as derived from the key. The right column is pitch in cents relative to the first tone of the scale. Internally, these numbers are stored to two decimal places.

If a scale with more than seven tones is being edited, the Edit Scale dialog appears:



The "set major scale" button, when clicked, will check tones in the remove column such that the remaining scale is a major scale. Similarly for "set minor scale".

If a scale with more than twelve tones is edited, the Edit Scale dialog appears:



The microtuning data at the bottom is presented as information to help you make decisions concerning what tones to include and exclude from the scale.



The Scale Detune slider

The Scale Detune slider allows the scale to be re-tuned. The values are cents (100 cents = a semitone). A value of zero implements the standard A3 = 440 Hertz. That is, if the key is D, the scale will have D as its root and will be tuned to D3 = 440 * 2 / 3 = 293.33 Hz which is exactly 600 cents below A3 = 440 Hz.

Moving the Scale Detune slider up, say to 20, will cause the scale to be raised up twenty cents in pitch. This will have the effect of tuning a soloist to a sharper scale. If you have a tone you know that you want to use as the pitch standard, select that tone and play it in a loop. Adjust Scale Detune until the Change meter reads zero. (You may be required to use the Edit Scale dialog to remove adjacent tones so that Auto-Tune doesn't tune to the wrong tone.)

You can Command-Click the Scale Detune slider to force it to zero.




The Retune slider

The Retune slider controls how rapidly the pitch correction is applied to the incoming sound. The units are milliseconds. A value of zero will cause instantaneous changes from one tone to another and will completely suppress a vibrato (note that any related volume changes will remain). Values from 10 to 50 are typical for vocals. Larger values let through more vibrato and other interpretative pitch gestures but also slow down how rapidly pitch corrections are made.



The Tracking slider


Auto-Tune requires a periodically repeating sound-wave, characteristic of a voice or solo instrument in order to track the pitch of the input. The Tracking slider controls how much variation in the incoming waveform is allowed. Usually you can set the Tracking slider to 25 and forget it. This control is useful with difficult to track sounds, such as a breathy voice, wind noise or a "Jimmy Durante" kind of growling voice. However, tracking is not guaranteed and a "relaxed" setting may introduce distortion and popping.



The Vibrato Section

The Vibrato Section contains one popup and three sliders. The Vibrato popup allows you to select the shape of the vibrato's pitch variation through time. The choices are: (no vibrato), sine wave, square and sawtooth. The Depth slider varies from 0 to 100 cents, controlling the amount of pitch variation in the vibrato. The Rate slider varies from .1 to 10.0 Hz and controls the speed of the vibrato. The Delay slider varies from 0 to 3000 milliseconds, controlling the speed of onset of the vibrato. For example, if it is set to 1000, the first 500 milliseconds of a new tone will contain no vibrato and the next 500 milliseconds will make a transition from no vibrato to the full vibrato.

The vibrato is re-started every time the Automatic Mode matches the incoming pitch to a different scale tone. Also, the vibrato is applied after the effects of the Retune slider. Hence, even with a slow retune value of 50, a square wave vibrato will make instantaneous changes in pitch.



The Change meter

The Change meter shows you how much the pitch is being changed, measured in cents (100 cents = one semitone).



Graphical Mode Controls

The Arrow buttons



The arrow buttons next to the Pitch Graph control the horizontal and vertical scaling of the graph.



The arrow buttons next to the Envelope Graph control the vertical scales as expected, but the left and right arrows are replaced by "all" and "tie". These control the horizontal scale: "all" shows the entire envelope recorded during pitch detection and "tie" slaves the scale and position of the Envelope Graph to that of the Pitch Graph.



The Graphical tools

These buttons are the graphical tools. They allow you to draw and edit the target pitch function.



The Line tool

Use this tool to click multiple points on the Pitch Graph. Line segments joining the points will be drawn. Any existing line or curve will be overwritten. If you move the cursor outside the Pitch Graph during point entry, the graph will be automatically scrolled.

To exit, double-click a point or press the <esc> on the keyboard.

To erase the last point entered, press the <delete> on the keyboard.



The Curve tool

Select this tool, then click and hold down the mouse on the Pitch Graph. A curve will be drawn out as the mouse is dragged. Any existing line or curve will be over-written. To exit, lift up on the mouse.



The Pointer tool

This tool is used to select and drag target pitch function objects (lines and curves). When this tool is selected, clicking on white space in the Pitch Graph causes all objects to become de-selected. Clicking on white space and dragging causes object end points to become selected. Shift-clicking (and dragging) can also be used to select contiguous points. Dragging off the Pitch Graph automatically scrolls the graph.

Every object (line or curve) has two end points. If both end points are selected, the object is said to be selected. If you click on an object which is not selected, it becomes selected. If you click on an object that is already selected, it (and anything else that is selected) stays selected so you can drag it.

Dragging causes the selected objects to be moved. Any objects that have one end-point selected will be stretched during dragging. Dragging is constrained by neighboring unselected objects.

If you hold down the option key and then click to drag, the cursor will be restricted to vertical only movements. This is particularly handy after using the "Make Curve" button, discussed below.



The Zoom/Select tool

Use the zoom/select tool in the Pitch Graph to press and drag a zoom box. After you lift the mouse, the scale and position of the Pitch Graph will be changed to show the area enclosed by the box. Dragging off the Pitch Graph automatically scrolls the graph.

This tool can also be used in the Envelope Graph to select a range of time, which allows the Make Curve button to become active.

undo

The Undo button

This is the Undo button. It becomes active whenever the target pitch curve is modified. Clicking it allows you to undo and redo the last change.

cut copy

The Cut and Copy buttons

The Cut and Copy buttons active whenever an object is selected. Cut removes selected objects. Cut and Copy move selected objects to the Auto-Tune clipboard. You can then paste the objects, elsewhere, in any Auto-Tune window.

paste

The Paste Button

The Paste button is active after objects have been cut or copied to the clipboard. Pressing it places the contents of the clipboard in the middle of the current Pitch Graph view. Hence be careful the Pitch Graph view does not contain anything you want to keep before you press paste.

select all

The Select All Button

The Select All button causes all target pitch function objects to become selected.

Keyboard equivalents:

The following are keyboard equivalents to the respective Graphical Mode buttons:

Command (Apple)Key	Function
a	Select All
z	Undo
x	Cut
С	Сору
v	Paste

TABLE 3. Edit Control Keys

make curve

The Make Curve button

The Make Curve button is enabled whenever there is any input sound pitch (red) data. If a range of time has been selected by applying the zoom/select tool in the Envelope Graph, the Make Curve button works in the selected time range only. Pressing the Make Curve button causes curve objects to be created from input sound pitch (red) data. These curve objects can then be dragged and stretched for very effective pitch correction. This technique is described in Chapter 3.

make auto

The Make Auto button

The Make Auto button is enabled whenever there is any input sound pitch (red) data. If a range of time has been selected by applying the zoom/select tool in the Envelope Graph, the Make Auto button works in the selected time range only. Pressing the Make Auto button causes curve objects to be

created from input sound pitch (red) data. The Make Auto computation uses the input sound pitch curve to precisely create target pitch function curves that are equivalent to the pitch of the Automatic Mode output. That includes the Scale edits, the Detune slider, the Retune slider and the Vibrato section.

Note that the Automatic Mode Tracking slider is not involved, because its function is used to determine the input sound pitch. In Graphical Mode, the input sound pitch has already been determined, (e.g. the red sound pitch curve), hence the Automatic Mode Tracking slider is not involved in the "make auto" computation.


After you use the Make Auto button, you may choose to hear the sound that would be produced in Automatic Mode. To do this, move the Retune slider to 0 (fast). This will faithfully reproduce the effect of the computed curve.



The Tracking slider

The DSP computes the pitch of the incoming sound during pitch tracking and pitch correction. The Graphical mode Tracking slider is similar in function but separate from the Tracking slider in the Automatic Mode. In both modes, it controls how much variation in the incoming waveform is allowed. Usually you can set the Tracking slider to 25 and forget it. This control is useful with difficult to track sounds, such as a breathy voice, wind noise or a "Jimmy Durante" kind of growling voice. However, tracking is not guaranteed and a "relaxed" setting may introduce distortion and popping.

Be cautious about changing the Tracking slider after performing the Track Pitch function. Auto-Tune uses the Tracking slider setting during Track Pitch and during Correct Pitch functions. Changing the Tracking slider settings will cause different parts of the sound to be pitch corrected. If you change this slider before Pitch Correction, your target pitch function may inadvertently make corrections you did not intend, possibly resulting is strange artifacts.



The Retune slider

The Retune slider is only used during pitch correction. It's similar in function but separate from the slider by that name in the Automatic Mode, however, the desired pitch is not the scale tone, but rather the target pitch function. This slider allows you to specify how quickly the algorithm will change the pitch of the input sound towards the target pitch function. A value of zero will cause the output pitch to equal the target pitch function, precisely. Depending on the target pitch function, this may give unnatural sounding results. Larger values will let you use simple line segments for the target pitch function and still let through the natural pitch gestures of the input sound.



The Playback controls



The Track Pitch button

After you select some sound for pitch correction, press this button. It will press in and flash "waiting". Next, start playback. When the first sound occurs, this button will show "tracking". The pitch and envelope of the sound is being recorded for display in the Pitch and Envelope Graphs. This recording will stop when any of the following happen: 1) The Track Pitch button is pressed again, 2) when the available buffer space (see below) is used up.

Cornect Pitch

The Correct Pitch button

After you have used the graphical tools to create a target pitch function, this button is used to apply the target pitch function to the incoming sound. You must press the button before playback is started. After it is pressed, it will flash"waiting". When playback begins and the first sound occurs, this button will show "correcting".

If you do not want pitch to occur, do not press the Correct Pitch button.



The Buffer size control

This control (the number can be edited) is the number of seconds of buffer space that are permanently reserved for pitch tracking and pitch correction data. 4,410 bytes/second are required for each buffer. There is a different buffer for each plug-in occurrence. If more space is requested than can be provided, you must increase Performer's size (select the Performer icon and press "Get Info" in Finder's "File" menu).

Index

```
Numerics
19 Tone 41
24 Tone 41
31 Tone 41
53 Tone 41
Α
accuracy 16
Arabic 1 41
Arabic 2 (chromatic) 41
Arrow buttons 46
artifacts 14
Automatic Mode 16, 24, 34, 36
  Controls 39
Automatic Mode Controls 21
Barnes-Bach (chromatic) 40
beat cycles 16
breathy voice 14
buffer 20, 25
Buffer size control 52
bypass button 16, 21
С
Carlos
  Alpha 41
  Beta 41
  Gamma 42
Carlos, Wendy 41
cent 12, 16
Change meter 24, 46
Command (Apple) Key 28
community orchestra 14
consonance 14
Contemporary Tunings 41
Copy button 48
Correct Pitch 20, 25, 26, 27, 29, 32, 33, 36
Correct Pitch button 52
Curve tool 27, 47
Cut button 48
cycle of fifths 41
cycles per second 12
D
Delay slider 45
Depth slider 45
```

desired pitch 19, 24 de-tune 17 Detune value 19 dissonance 14 dissonant 12 do not track 22, 23, 43 drawing tools 20 DSP 11

Ε

Edit Scale button 22, 23, 36, 42 Edit Scale dialog 23, 43 end points 27 Envelope Graph 19, 46 EQ 15 Equal Tempered Scale 13, 23, 39 error 16 ethnic scales 17 Ethnic Tunings 40

Fast Fourier Transform 15 FFT 15 frequency 11 fundamental 11, 16

G

graphical editor 20 Graphical Mode 16, 18, 24 Graphical Mode Controls 46 Graphical tools 20, 25, 47 Greek chromatic genus 40 Greek diatonic genus 40 Greek enharmonic genus 40

Н

Hal Leonard Books 39 Harmonic (chromatic) 42 harmonics 11, 16 harmonies 14 harmonious 12 Hertz 12, 14 highest pitch 15 historical scales 17 Historical tunings 40 horizontal scale 19 Hz. 12

```
Indian 40
Infinity 14
Installing 9
interference
  constructive 16
  destructive 16
intervals 12
intonation 14
J
Just (minor chromatic) 40
key annotation 19
Key popup 21, 25, 42
Keyboard equivalents 28, 49
Line tool 26, 47
  double-click 26
  erase 26
Ling Lun 40
loudness gestures 33
М
Make Auto button 34, 36, 49
Make Curve button 30, 31, 33, 48, 49
Meantone chrom. 40
microtonal scales 17
Microtonal tuning data 23
microtuning data 44
natural pitch corrections 30
non-periodic 15
0
octave 12
output pitch 16
Partch, Harry 41
Paste Button 48
Pelog 41
periodic waveform 14
phase 16
phase errors 15
```

```
pitch 11, 12, 15
  correction 13, 15
  detection 14
  gestures 33
  shifting 15
  standard 24, 42, 44
  variation 15
Pitch Graph 19, 24, 27, 46
Playback controls 51
Pointer tool 27, 47
precision of correction 16, 30
precision of detection 15
processing delay 14
pure intervals 40
pure perfect fifths 40
Pythagorean 40
R
Rate slider 45
ratios of frequency 12
remove 22, 36, 43
Retune slider 17, 21, 23, 27, 45
  fast 17, 23
  slow 17, 23
S
scale 16
  chromatic 17
  major 17
  minor 17
  names 19
  pitches 19
Scale Detune slider 24, 44
Scale popup 39, 43
Scholar's Lute 40
Select All button 49
semi-tones 13
set major scale 22, 44
set minor scale 22, 44
settings 37
settling time 34
Slendro 40
synthesizer 13
synthetic sweep signal 21
Т
target pitch function 18, 20, 24, 25
Technical Support 10
time-of-day 20, 37
```

```
tonality 17
Track Pitch button 20, 25, 51
tracking 16
Tracking slider 15, 45, 50
transparent 15
Tremolo 33
U
Undo button 48
Vallotti & Young chrom. 40
vibrating element 11
Vibrato
  popup 45
vibrato 17, 37
  delay 17
  depth 17
  popup 24
  rate 17
Vibrato Section 17, 45
W
waveform 11
  non-periodic 12, 14
  periodic 12
Werckmeister III chrom. 40
Western tonal music 13
Wilkinson, Scott R. 39
wind sound 14
Z
Zoom/Select tool 26, 31, 35, 48
```